

Software installation (on computer) for Tek MDO34 Scope

Need to install the following:

Tkdpo2k3k4kIVIDriver1.5_066133104.exe

OpenChoiceTekVisa_Deployment_Package_066093812.exe

ni-visa_19.0_online.exe: (download from <http://www.ni.com/download/ni-visa-run-time-engine/7222/en/>)

TekScope Utility 1.2.0.7 – entire folder goes to C:\Program Files (x86)

Create shortcut for TekScope Utility.exe

Put shortcut into C:\ProgramData\Microsoft\Windows\Start Menu\Programs\Tektronix


OpenChoiceTekVisa_Deployment_Package installs the following:

NET 4.0

VC++ X86 2010 redistrib v10.0.0.40219

VC++ X64 2010 Redistributable

OpenChoice TekVisa v4.2.0.26




Running the program

From Start menu:

Select Tektronix → TekScope Utility

If a dialog asks “Search for app in the Store?”, select No.

When program starts, click on  **Select Instrument**

Next, select your scope by IP address or serial number

Click OK

Then, under the Waveform tab, click the appropriate channel, then click the Get Data button to acquire the waveform image and data.

To save the waveform data, click the Save As... button, then browse to your preferred location to save your data as a comma-delimited file.

Instrument ID:

Hard Copy

Waveform

Measurements

Setup

Data Logger

Console

Save As...

Get Hard Co

VISA Address: Select Instrument Status: None